

QUANTUMloop Firmware Update

October 2018

How to update:

1. Plug in USB cable and 9v power cable
2. The QUANTUMloop will enter into update mode.
3. Windows will find the "Duet" drives and you can find the USB device.
4. Select "Ortega QUANTUMLoop V2.exe" right-click QUANTUMloop software application and select: "Run as administrator"
5. Select "Ortega QUANTUMloop" and click "Connect"

If here does not display the "Ortega QUANTUMLoop", please use QUANTUMLoop. V1(old) software version to connect. Than repeat the step 1 to steps 5 .

6. Select firmware to update and upload firmware.

fwupdate_V54_no delay.dat	Looper button without delay version
fwupdate_V55.dat	Looper button without delay version

7. Finish update, turn off the power and plug out the cable.

